LV07: Statičko usmjeravanje

Priprema za vježbu:

1) Na koji način se informacije o putanji do odredišta unose u usmjerničku tablicu kod statičkog usmjeravanja?

U statičkom usmjeravanju, informacije o putanji do odredišta unose se ručno ili statički (konfiguriraju) na usmjerniku

Postupak obično uključuje ručno postavljanje usmjerničke tablice na temelju administrativnih odluka mrežnog administratora

Statičko usmjeravanje je manje fleksibilno od dinamičkog usmjeravanja jer ne reagira automatski na promjene u mreži; Međutim, može biti prikladno u manjim mrežama ili u situacijama gdje je kontrola nad usmjeravanjem važnija od brzine prilagodbe na promjene

2) Kako izgleda sintaksa za konfiguraciju statičke rute? Objasni na primjeru!

Sintaksa za konfiguraciju statičkih ruta može se razlikovati ovisno o vrsti usmjernika i OS-u koji koristi

Ovo je primjer sintakse za konfiguraciju statičke rute na Cisco usmjernicima s OS-om IOS:

ip route <odredište> <mrežna maska> <sljedeća točka>

<odredište> predstavlja IP adresu ili mrežu do koje želimo postaviti rutu

<mrežna maska> označava mrežnu masku koja identificira koji dio adrese se odnosi na odredište

<sljedeća točka> je adresa sljedeće točke (next-hop), odnosno adresa usmjernika prema kojem će paketi biti proslijeđeni kako bi došli do odredišta

Primjer konfiguracije statičke rute za slanje paketa prema mreži 192.168.2.0/24 preko sljedeće točke s IP adresom 10.0.0.1:

ip route 192.168.2.0 255.255.255.0 10.0.0.1

Izvođenje vježbe:

1) Spojiti usmjernik R1 sa računalom u ulozi terminala, rollover kabelom, kao na slici.

Dvostrukim klikom odaberemo karticu Desktop, a zatim Terminal.

Zadržati predložene postavke terminala.

Na ponuđeno pitanje: Continue with configuration dialog? [yes/no] odgovorimo sa : no

1841		
Router0		
+		
PC-PT PC0		
	2411-10-10-20	
vsical Contio Desktop Programming	ATTIDUTES	
nysical Config Desktop Programming	Attributes	
rysical Config Desktop Programming	Attributes	×
nysical Config Desktop Programming erminal Configuration Port Configuration	Attributes	×
rysical Config Desktop Programming erminal Configuration Port Configuration Bits Per Second:	9600	×
rysical Config Desktop Programming rminal Configuration Port Configuration Bits Per Second: Data Bits:	9600 8	~
nysical Config Desktop Programming erminal Configuration Port Configuration Bits Per Second: Data Bits: Parity:	9600 8 None	×
rysical Config Desktop Programming erminal Configuration Port Configuration Bits Per Second: Data Bits: Parity: Stop Bits:	9600 8 None 1	× ~ ~
rysical Config Desktop Programming erminal Configuration Port Configuration Bits Per Second: Data Bits: Parity: Stop Bits: Flow Control:	Attributes 9600 8 None 1 None	× × ×

2) Usmjernik koji prvi puta konfiguriramo trebao bi se nalaziti u početnom (defaultnom) stanju.

Kako bismo bili potpuno sigurni da je tako, potrebno je izvršiti brisanje NVRAM-a od mogućih tragova prijašnjih konfiguracija.

```
Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files! Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#reload
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)
Initializing memory for ECC
```

3) Ulazak u pojedine CLI modove.

a) Ulazak u privilegirani mod:

```
Router>enable
Router#
```

b) Ulazak u globalni konfiguracijski mod:

```
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
```

c) Ulazak u konfiguracijski mod usmjernika:

```
Router(config) #router rip
Router(config-router) #
```

d) Ulazak u konfiguracijski mod sučelja:

Ovdje je potrebno vratiti se korak natrag radi vraćanja u globalni konfiguracijski mod, naredbom exit

```
Router(config-router)#exit
Router(config)#interface Fastethernet 0/0
Router(config-if)#
```

e) Doznačavanje imena usmjerniku, ali iz globalnog konfiguracijskom moda (exit):

```
Router(config-if)#hostname RB
RB(config)#
```

4) Pomoćne naredbe.

exit vraćanje u niži mod end vraćanje u

privilegirani mod iz bilo kojeg moda disable vraćanje iz

privilegiranog moda u korisnički mod history prikazuje

nekoliko prethodno zadanih naredbi Strelica prema gore prikazuje

prethodnu naredbu

? pokazuje koje su naredbe na raspolaganju

5) Konfiguracija zaporki usmjernika – koristiti zaporke "skola" i "razred" naizmjence.

a) Zaštita od neovlaštenog pristupa usmjerniku putem konzole:

```
RB(config)#line console 0
RB(config-line)#password skola
RB(config-line)#login
```

b) Zaštita od neovlaštenog pristupa usmjerniku putem Telneta:

```
RB(config) #line vty 0 4
RB(config-line) #password razred
RB(config-line) #login
```

c) Zaštita od neovlaštenog pristupa privilegiranom modu:

```
RB(config)#enable password skola
RB(config)#exit
RB#
%SYS-5-CONFIG_I: Configured from console by console
RB#
```

d) Poruka upozorenja:

RB(config)#banner motd %Oprez - sva spajanja se nadziru%

Operacijski sustav omogućava da se prilikom priključivanja na ruter putem telneta, na terminalu pokaže poruka upozorenja, kao na primjer: "Oprez - sva se spajanja nadziru"

6) U privilegiranom ili u korisničkom modu pored prompta ukucajte kombinaciju slova koju IOS ne razumije (npr. svoje ime):

Router>Patrik

Odgovor operacijskog sustava će biti: Translating "patrik"...domain server (255.255.255.255), poslije čega slijedi pauza koja traje oko 40 sekundi.

Da biste to izbjegli potrebno je u globalnom konfiguracijskom modu ukucati slijedeće naredbu:

7) Provjera i pohranjivanje konfiguracije.

a) Ako želimo vidjeti kako se ruter ponaša kod uporabe zaporki, vratit ćemo se u korisnički mod:

RB#disable RB>

Pokušavamo ući u privilegirani mod:

RB>enable Password:

Unosimo zaporku za privilegirani mod (Točka 5 c) i dobivamo:

RB#

b) Pohranjivanje do sada izvršene konfiguracije izvodimo na poznati način:

```
RB#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
RB#
```

c) Ukoliko poželimo vidjeti konfiguraciju koja je pohranjena, zadajemo naredbu:

RB#show running-config

d) Odspojiti terminal, isključiti ruter prekidačem (kartica Physical), a zatim sve ponovno spojiti.

Da li su sve postavke na ruteru zadržane?

Sve su postavke na ruteru zadržane.

Statičko usmjeravanje:



Uređaj	Adresa fastethernet sučelja	Oznaka sučelja	Mrežna maska	Oznaka Serijskog sučelja	Tip serijskog sučelja	Adresa serijskog sučelja	Mrežna maska	Default gateway
R1	192.168.20.193	0/0	255.255.255.192	S2/0	DCE	172.16.30.1	255.255.255.252	
	192.168.80.65	1/0	255.255.255.192					
R2				S2/0	DTE	172.16.30.2	255.255.255.252	
PC1	192.168.20.194							192.168.20.193
PC2	192.168.20.195							192.168.20.193
PC3	192.168.80.66							192.168.80.65
PC4	192.168.80.67							192.168.80.65

1) U PT-u spoji uređaje prema zadanoj topologiji i izvrši temeljnu konfiguraciju usmjernika, koristeći spojena računala kao terminale (rollover kabel).

Na R2 također dodaj terminal radi konfiguracije.

2) Konfiguriraj sučelja na usmjerniku R1, koristeći priloženu tablicu adresa.

Postupak za usmjernik R1:

a) Konfiguracija fastethernet sučelja:

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/2.
Router(config)#interface fastethernet 0/0
Router(config-if)#ip address 192.168.20.193 255.255.255.192
Router(config-if)#no shutdown
```

Ponoviti postupak i za sučelje FE 1/0

```
Router(config)#interface fastethernet 1/0
Router(config-if)#ip address 192.168.80.65 255.255.192
Router(config-if)#no shutdown
```

b) Konfiguracija serijskog sučelja 2/0 (DCE)

```
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface serial 2/0
Router(config-if)#ip address 172.16.30.1 255.255.255.252
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#
```

- 3) Konfiguriraj sučelje na usmjerniku R2, uz pomoć tablice adresa
- a) Konfiguracija serijskog sučelja 2/0:

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/2.
Router(config)#interface serial 2/0
Router(config-if)#ip address 172.16.30.2 255.255.255.252
Router(config-if)#no shutdown
Router(config-if)#
```

4) Pinganjem provjeri da li postoji povezanost između računala u jednoj i drugoj Ethernet mreži.

```
Command Prompt

Cisco Packet Tracer PC Command Line 1.0

C:\>ping 192.168.80.66

Pinging 192.168.80.66 with 32 bytes of data:

Request timed out.

Reply from 192.168.80.66: bytes=32 time<1ms TTL=127

Reply from 192.168.80.66: bytes=32 time<1ms TTL=127

Reply from 192.168.80.66: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.80.66:

Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

5. Pinganjem provjeri dohvatljivost default gatewaya za svaku mrežu.

```
C:\>ping 192.168.80.65
Pinging 192.168.80.65 with 32 bytes of data:
Reply from 192.168.80.65: bytes=32 time<lms TTL=255
Reply from 192.168.80.65: bytes=32 time<lms TTL=255
Reply from 192.168.80.65: bytes=32 time<lms TTL=255
Ping statistics for 192.168.80.65:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\>
```



6. Pinganjem sa bilo kojeg računala provjeri dohvatljivost serijskog sučelja S2/0 usmjernika R2 (iz naredbenog retka - cmd).



7) U simulation modu uputi ICMP paket sa bilo kojeg računala na R1, a zatim na R2.



8) Naredbom show ip route na usmjernicima R1 i R2 provjeri stanje ruting tablice.

```
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.16.0.0/30 is subnetted, 1 subnets
С
       172.16.30.0 is directly connected, Serial2/0
     192.168.20.0/26 is subnetted, 1 subnets
С
       192.168.20.192 is directly connected, FastEthernet0/0
     192.168.80.0/26 is subnetted, 1 subnets
С
       192.168.80.64 is directly connected, FastEthernet1/0
Router>
```

```
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
172.16.0.0/30 is subnetted, 1 subnets
C 172.16.30.0 is directly connected, Serial2/0
Router>
```

9) Konfiguriraj statičku rutu na R2

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/2.
Router(config)#ip route 192.168.20.192 255.255.255.192 172.16.30.1
Router(config)#ip route 192.168.80.64 255.255.255.192 172.16.30.1
```

10) Naredbom show ip route na oba usmjernika provjeri stanje usmjerničkih tablica.

```
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D = EIGRP, EX - EIGRP external, O - OSFF, IA - OSFF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
172.16.30.0 is directly connected, Serial2/0
192.168.20.0/26 is subnetted, 1 subnets
C 192.168.20.192 is directly connected, FastEthernet0/0
192.168.80.0/26 is subnetted, 1 subnets
C 192.168.80.0/26 is directly connected, FastEthernet1/0
Router>
```

```
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.16.0.0/30 is subnetted, 1 subnets
С
       172.16.30.0 is directly connected, Serial2/0
     192.168.20.0/26 is subnetted, 1 subnets
       192.168.20.192 [1/0] via 172.16.30.1
s
    192.168.80.0/26 is subnetted, 1 subnets
       192.168.80.64 [1/0] via 172.16.30.1
s
Router>
```

11) Pinganjem provjeri povezanost sa usmjernikom R2 sa jedne i druge Ethernet mreže.

```
C:\>ping 172.16.30.2
Pinging 172.16.30.2 with 32 bytes of data:
Reply from 172.16.30.2: bytes=32 time=7ms TTL=254
Reply from 172.16.30.2: bytes=32 time=17ms TTL=254
Reply from 172.16.30.2: bytes=32 time=7ms TTL=254
Reply from 172.16.30.2: bytes=32 time=15ms TTL=254
Ping statistics for 172.16.30.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 7ms, Maximum = 17ms, Average = 11ms
C:\>
C:\>ping 172.16.30.2
Pinging 172.16.30.2 with 32 bytes of data:
Reply from 172.16.30.2: bytes=32 time=26ms TTL=254
Reply from 172.16.30.2: bytes=32 time=29ms TTL=254
Reply from 172.16.30.2: bytes=32 time=28ms TTL=254
Reply from 172.16.30.2: bytes=32 time=29ms TTL=254
Ping statistics for 172.16.30.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 26ms, Maximum = 29ms, Average = 28ms
C:\>
```